

# Configuration Overview

In this section:

- [Configuring the Settings](#)
- [Settings Hierarchy](#)
- [Viewing Current Settings](#)
- [JVM, Framework, and Application Setup](#)

## Configuring the Settings

Jtest DTP Engine can be configured with settings (see [Configuration Settings](#)) that should be specified in a `.properties` file. The basic settings are listed in the `jtestcli.properties` file shipped in `[INSTALL_DIR]`. For your convenience, you can also store common settings in a `jtestcli.properties` file in the `$USER_HOME` directory to overwrite settings stored in the properties file in the `[INSTALL_DIR]` directory.

You can also create a custom `.properties` file and pass it to the `jtestcli` with the `-settings` switch. Use absolute paths to specify the custom `.properties` file. You can use the `-settings` switch multiple times to specify several `.properties` files. Entries with the same key will be overwritten.

```
jtestcli -settings path/to/settings.properties -settings path/to/another/settings.properties
```

## Settings Hierarchy

General settings are applied in the following order:

1. `[INSTALL_DIR]/etc/jtestcli.properties`: the base configuration file that **should not be modified**.
2. `[INSTALL_DIR]/jtestcli.properties`: the main configuration file you can use to specify your settings that map contains templates for commonly used settings (license, reporting etc.).
3. `[USER_HOME]/jtestcli.properties`: for your convenience, you can store the configuration file in your home directory to overwrite settings from the `[INSTALL_DIR]` (for example, to ensure your settings are not affected by reinstallations or updates).
4. `[WORKING_DIR]/jtestcli.properties`: for your convenience, you can store the configuration file in your working directory.
5. Custom settings passed with the command line switch `-settings path/to/settings.properties` (e.g., `-settings ../settings.properties`).
6. Custom settings passed with the command line switch `-property [key=value]`.

All of the above settings can be overridden by custom settings that are passed with command line switches (e.g. `-report`, `-config`).

## Ant and Maven Pattern

You can provide the path to the settings file with Ant or Maven using the following pattern:

```
<settings>path/to/settings.properties</settings>
```

## Settings Hierarchy for Maven

If you use Maven, you can configure jtestcli settings with:

- `-Djtest.[Maven property name]` (e.g., `-Djtest.settings="my.general.properties"`).
- the `pom.xml` file
- `-Dproperty.jtest.[property name]` (e.g., `-Dproperty.jtest.license.use_network=true`)

Both `-Djtest` and `pom.xml` override settings that are passed with `-Dproperty.jtest`.

`-Djtest` overrides settings in `pom.xml` if they are provided as user properties. However, if a setting value is specified directly in `pom.xml`, it has the highest priority and cannot be overridden by command line settings. For example, the test configuration specified in `pom.xml` as a user property `<config>${jtest.config}</config>` can be overridden with `-Djtest.config`. If it is hardcoded as `<config>builtin://Demo Configuration</config>`, it cannot be overridden.

See the Jtest Goal page in `plugins-manual.html` for the complete list of parameters.

It is recommended that you keep all user-level customizations, including custom settings, license, rules, test configurations, compiler configurations, outside of the Jtest installation directory so they are not affected by reinstallations or updates.

# Viewing Current Settings

Use the `-showsettings` option to print the current settings and customizations, including the origin file for each configuration.

## Ant and Maven Pattern

If you use Ant or Maven, you can use the following pattern to view the current settings:

```
<showsettings>true</showsettings>
```

# JVM, Framework, and Application Setup

The following table describes additional configuration files for setting up Jtest DTP Engine.

File	Description	Directory
<code>jtestcli.properties</code>	Contains the default settings for the Jtest properties.	[INSTALL_DIR]
<code>jtestcli.jvm</code>	Contains JVM arguments that the <code>jtestcli.exe</code> ( <code>jtestcli</code> ) executable will use when starting Java processes.	[INSTALL_DIR] /etc
<code>framework.properties</code>	Contains properties that are passed to the launched Felix OSGI framework. There is typically no need to edit this file.	[INSTALL_DIR] /etc
<code>formatting.properties</code>	Contains formatting rules for the default Jtest properties.	[INSTALL_DIR] /etc
<code>logging.xml</code>	Logger configuration file; outputs a silent console by default and warn level on the <code>jtest.log</code> file.	[INSTALL_DIR] /etc
<code>logging.console. debug.xml</code>	Logger configuration with debug level on the console output.	[INSTALL_DIR] /etc