

Windows Standalone

This topic explains how to install the standalone version of C++test (which is built on the Eclipse framework) on a Windows system.

The section includes:

- [About Multi-user Installations](#)
 - [Shared Configuration \(Recommended\)](#)
 - [Shared Installation](#)
- [Prerequisites](#)
 - [System Requirements](#)
 - [Other Requirements](#)
- [Installation](#)
- [Startup](#)
- [Licensing](#)

About Multi-user Installations

Each instance of Eclipse creates and writes to a configuration folder. If multiple instances of Eclipse/C++test are running in parallel, data corruption may occur. Eclipse provides a number of strategies for initializing the Eclipse configuration area in order to support multi-user installations.

The shared configuration described below is the recommended installation scenario implementing a multi-user installation of C++test. Refer to the Eclipse documentation for additional information.

Shared Configuration (Recommended)

In this scenario, users share not only an install area but also a master configuration area. By default, users must still have their own private writable configuration areas. A user's private configuration area is cascaded to the master configuration and will not contain any interesting data if the master configuration has been fully initialized and no changes to the set of plug-ins to be installed has occurred.

In this scenario, the system administrator initializes the master configuration (typically under the install location), and ensures the whole install and configuration areas are read-only to users. When users run the Eclipse-based product from the shared install location, since they do not have write access privileges to the configuration area under the install area, a local configuration area will be automatically computed and initialized.

Shared Installation

In this scenario, a single install area is shared by many users. The 'configuration' directory under the install area is home only to the config.ini as shipped with the product (it is not initialized). Every user has their own local standalone configuration location. This scenario requires making the install area read-only for regular users. When users start Eclipse, this causes the configuration area to automatically default to a directory under the user home dir.

Prerequisites

System Requirements

- One of the following platforms:
 1. Windows 7, Windows 8, Windows 10 (with an x86-compatible processor).
 2. Windows 7 x64, Windows 8 x64, Windows 10 x64, Windows Server 2008 x64 (with an x86_64-compatible processor), Windows Server 2012.
- 1.5 GHz or higher processor.
- 4 GB RAM (8 GB is recommended).
- A supported compiler or cross-compiler.
 - See [Supported Environments](#) for a list of supported compilers.

Proper Compiler Configuration is Critical

In most cases, C++test needs to invoke the compiler and linker in order to perform static analysis and runtime testing tasks, which commonly involve preprocessing, compiling, and linking programs.

To access C++test's full functionality, the machine where C++test is run must have the complete development environment and compiler tool chain.

Windows and Windows Server notes

- Installation and initial run must be performed by a user with Administrator privileges.
- When running C++test, you must have write access to the directory containing the testing workspace and project. Specifically, if you are using a non-Administrator account, you will need to copy C++test example projects from the 'Program Files' location into the user directory and run the tests on the copied projects.
- The C++test CLI executable (cpptestcli.exe) should be executed from a directory with write access (because the working directory is the default location in which C++test generates the report after tests).
- If your machine-id is WIN32-0, remove the file located in <DRIVE>:\Users\<USER_NAME>\.parasoft\C++test\9.x\license.

Other Requirements

- If earlier versions of C++test are installed on your system, the latest version of C++test must be installed in a new directory.
- Additional disk space is required for C++test project data.
- The recommended Japanese language encoding is Shift_JIS (ja_JP.PCK locale on Unix). Other encodings might cause font problems or prevent C++test from reading test results.

Alternative installation methods

For details on performing a silent installation see [Preconfiguration C++test During Installation](#).

Installation

To install the standalone version of C++test on a Windows system:

1. In Windows Explorer, locate and double-click the self extracting archive.
2. Click **Yes** when a dialog asks whether you want to install C++test.
3. Select the language to use during the installation.
4. Click **Next** after you have read and agreed with the license information.
5. In **Destination Location**, enter the desired installation directory for C++test's files, then click **Next**.
 - If Parasoft Test 9.x is not yet installed, you will be asked to select an installation directory for Parasoft Test's files.
 - If Parasoft Test 9.x is already installed, C++test will be installed into it.
6. Specify where you want the program's shortcuts added in the Start Menu Folder.
7. Click **Install**.

C++test will be installed in the specified installation directory.

Startup

Before launching C++test

For C++test to autodetect compiler and makefile settings, the necessary executables (compiler/linker, makefile, etc.) must be correctly configured. "Correctly configured" means different things for different compilers, but it typically involves ensuring that the executable is on the PATH.

To launch the standalone, do one of the following:

- Launch the cpptest executable. Include the appropriate location (install dir) on the \$PATH or launch it with the full path to the executable.
- Double-click the C++test desktop shortcut.

After Eclipse is launched, you should see a **Parasoft** menu added to the Eclipse menu bar. If you do not see this menu, choose **Window> Open Perspective> Other**, select **C++test**, then click **OK**.

If you suspect that C++test is not properly installed, see [Troubleshooting and FAQs](#) for help resolving some common installation problems.

Licensing

The license is configured through the centralized licensing framework (**Parasoft> Preferences> Parasoft> Licenses**). For details, see [Licensing](#).