

Configuring License Server

1. Open the **License Server** home page.
2. Choose **General > License Server Configuration** and configure the settings.

License Server configuration

[\[Back\]](#)

License Server port: Note: Additional configuration changes are required when changing the port.

Clients should start deactivated:

Concurrent connections limit:

Access logs management

Log cleaning

Remove log files older than days.

Use log files from location:

Note: It is not recommended to change the default path.

default (C:\Users\annstu\Desktop\LS2\license-server\tomcat\logs)

[\[Save\]](#)

The following settings are available:

License Server Port	Displayed by default after the default installation. You must restart services if you change the port. See Starting DTP Services . You can disable access to the port if are not using Licenser Server in your organization. See Disabling the License Server Port .
Clients should start deactivated	Enabling this option forces connected Parasoft tools to start deactivated. See the Parasoft tool documentation settings for additional information.
Concurrent connections limit	This option sets maximum number of tool requests (connections to License Server) that can be processed concurrently. By default, it is set to 100.
Log cleaning	Specify how many days logs are stored before automatically being removed from database.

**Use log files
from the
location**

Specifies where access logs are stored. The default path is recommended. If you reconfigured the log file access location, specify that path to point License Server appropriately. This allows License Server to remove old logs.