

# XML Data Bank

This topic explains how to configure and apply the XML Data Bank tool in SOAtest and Virtualize. This tool that extracts XML values (e.g., from a request or response message) so that they can be used in another place. Data can also be sent to a Writable Data Source and accessed in the Extension Tool, or it can be sent to variables for easy reuse across the test suite (SOAtest) or Responder suite or Action suite (Virtualize).

Sections include:

- [Understanding XML Data Bank](#)
- [Configuring XML Data Bank Using the Data Source Wizard](#)
- [Configuring the XML Data Bank Manually](#)
- [Configuration Options](#)
- [Viewing the Data Bank Variables Used During Test Execution](#)
- [Parameterizing XPath](#)
- [Handling Empty/Missing Elements to Maintain the Integrity of the XML Response](#)
- [Related Tutorials](#)

## Understanding XML Data Bank

The XML Data Bank tool enables you to extract certain XML values (e.g., from a request or response message) so that they can be used in another place. The XML Data Bank tool can be chained to any other tool that outputs XML. It can extract any information from the XML and make that information available for later use.

For example, you can configure a test suite that tests a bank's Web service transactions. Test 1 of that test suite can log on to the service using a User ID, then the SOAP response would return a session ID back to Test 1. Test 2 of that test suite can be configured to use the session ID from Test 1 to perform transactions. You can configure any of the tests in a test suite to use SOAP response parameters as SOAP request parameters.

Users typically configure an XML Data Bank by accessing the "Use Data Source Wizard" while parameterizing a value in a tool such as the SOAP Client or Messaging Client tool. This provides a quick, intuitive, and largely automated way to extract data from one tool and use it another. You simply go to the tool where you want to insert extracted data, then use a wizard to specify what data (e.g., from what tool) you want to extract. This is the usage model demonstrated in the Storing Results to Be Used in Subsequent Tests tutorial. This same method can be used to extract data that is used to set a variable. Alternatively, you can manually configure an XML Data Bank tool to extract data from one tool, then manually configure other tools to use the extracted values.

## Video Tutorial

In this video, you'll learn how to extract values from XML responses and reuse them in other tests.

[Configuring XML Data Bank Using the Data Source Wizard](#)

### Configuring the Extraction

To use the "Use Data Source Wizard" wizard to configure an XML Data Bank:

- In the configuration panel for the tool that you want use the extracted value, select one of the available Form views.
- From the **Operation** drop-down menu, select the operation that you want to use the extracted value.
- In the wizard that opens:

Select the tool you want to extract a value from. The drop-down menu at the top of the panel will contain all tools in the test or Responder suite that occur before the current tool you are configuring. For example, if you are configuring Tool 4, tools 1, 2, and 3 will display in this menu along with any data sources that may be available.

Using the controls on the left side of the panel, indicate what you want to extract and add it to the right side of the panel. The right panel lists the values you have configured for extraction, and shows the name of the data source column where they will be stored (if you keep the default setting).

(Optional) If you want to specify additional options (e.g., if you want to change the name of the column used to store the value, you want the value saved to a writable data source, or you want the value stored to an existing variable) —or if you want to modify advanced XPath settings—then select the appropriate element in table on the right and click **Modify**. Next, configure the options as needed, then click **OK**.

Available options are described in [XML Data Bank - Options for Each Extracted Element](#).

### Configuring the XML Data Bank Manually

You can also manually chain the XML Data Bank tool to a tool within the Responder, Action, or test suite. To configure the XML Data Bank as a chained tool, complete the following:

- Right-click the node for the tool associated with the data you want to extract.
- Choose **Add Output** wizard, indicate where you want to extract the value from (e.g., SOAP Envelope) and click the **Finish** button. An **XML Data Bank** node displays below the tool.
- Configure the tool as follows:

Use the available controls to specify the XPath that indicate what value you want to extract. To add an XPath, select a value from the **Expected Message** list and click the **Extract Element** button. The value you added displays in the **Selected Element** list with a Data Source Column name containing the name of the value came from, as well as the extracted value.



The left panel displays the expected XML response used to create a template from which you can select elements. If this tool receives a valid XML message (e.g., from traffic or as defined by the client tool it is attached to), this panel will be populated automatically. Alternatively, you can copy a sample message into the **Literal** or **Tree** tabs. Note that the expected XML does not get saved by default; if you want to save it, enable the **Save Expected XML** option.

If you want to further configure the XPath or customize extraction settings for this element, click **Modify**, then modify it as desired. See [XMLDataBank-OptionsforEachExtractedElement](#) for details.

Repeat steps a and b as needed to configure any additional extractions you want performed.

In the bottom area of the XML Data Bank configuration panel, customize the options as desired. See [XMLDataBank-Tool-WideExtractionOptions](#) for details.

### Using the Extracted Value

After adding and/or modifying the extraction, configure the tool that you want to use the extracted data.

Set the value to **Parameterized**, and choose the appropriate item from the drop-down. For example, if you saved the value to the `&quot;title&quot;` data source column, you would select it as follows.



### Configuration Options

You can configure the following options when configuring an XML Data Bank:

- Options for Each Extracted Element**
- Tool-Wide Extraction Options**

### Options for Each Extracted Element

The following options can be set by modifying a selection listed in the right panel of the XML Data Bank configuration panel.

**XPath Options**

- XPath**: Displays the XPath indicating the value to extract. If you are looking for a more general XPath, you can easily type in a different number into the list indices. For example `[1]` can be changed to `[2]` if you are interested in the 2nd occurrence only. After editing the XPath text, click the **Validate** button to validate the XPath format, click **OK**.
- Extract**: Allows you to specify exactly what is extracted.
- Entire Element**: Selecting **Entire Element** will output the entire XPath. For example, `XPath/Parent` will output `&lt;parent&gt;VALUE&lt;/parent&gt;`. You can configure **Index to extract**, which controls which element is extracted if the element occurs more than once.
- Content Only**: Selecting **Content Only** will output only the value. For example, `XPath/Parent` will output `VALUE`. You can configure **Text Content**, which extracts the text content of the element selected, or **All Child Nodes**, which extracts all child nodes of the element selected.
- XPath Evaluation**: Clicking the **Evaluate XPath** button displays the result of applying the XPath expression against the expected XML.

**Data Source Column Options**

- Custom column name**: Specifies the name of the data source column in which to store the value. Values are stored in an internal data source unless you specify otherwise (e.g., if you select **Writable data source column** or **Variable**). This is the name you will use to reference the value in other places. For example, if it is stored in a data source column named `My Value`, you would choose `My Value` as the parameterized value. You could also reference it as `$(My Value)` in literal or multiple response views.
- Writable data source column**: Enables storing the value in a writable data source column (see [display/SOA9103/Parameterizing+Tests+with+Data+Sources%2C+Variables%2C+or+Values+from+Other+Tests#ParameterizingTestswithDataSources,Variables,orValuesfromOtherTests-ConfiguringWritableDataSource](#) for details). This allows you to store an array of values. Other tools can then iterate over the stored values.
- Write to all columns that match**: Enables storing the value in all columns whose name contains the specified string. When extracting multiple values from a message, each value will be written across all the columns that match. In contrast, if you pick a single writable data source column (the above option), then the values will be written down the column across multiple rows.
- Variable**: Enables saving the value in the specified variable so that it can be reused across the current **Responder**, **Action**, or **test suite**. The variable must already be added to the current suite as described in [pages/viewpage.action?pagelId=27522414#ConfiguringTestSuiteProperties-TestFlowLogic,Variables,etc.-DefiningVariables](#).

Any values set in this manner will override any local variable values specified in the **Responder**, **Action**, or **test suite** properties panel.

### Tool-Wide Extraction Options

The following options can be configured in the lower portion of the XML Data Bank tool configuration panel.

- Save expected XML**: Specifies whether or not to save the expected XML.
- Canonicalize XML output**: Specifies whether or not an extracted element is canonicalized. If this option is selected, and if an entire element is extracted, any necessary namespace declarations are added to the extracted element if the element contains prefixes referencing namespaces that are not declared in the same element.
- Allow alteration**: Specifies whether to allow the alteration of an XPath. When this option is selected, an **Extract** tab and an **Alter** tab display beneath the **Selected Element** list. To alter an XPath, select the **Allow alteration** check box, select the **Alter** tab, add an XPath by clicking the **Extract Element** button, and then modify the XPath by clicking the **Modify** button. The **Modify** dialog displays and contains the following options:
  - XPath**: Displays the selected XPath. To edit and validate a selected XPath, edit the XPath text, click the **Evaluate XPath** button to validate the XPath format, then click **OK**.

